

Extending Disk Space

Depending on your environment you may need to enlarge the virtual disk on which the data is stored.






Please note that all virtual disks have to be located on the same physical storage. Please also note that extending disk space ALWAYS means that you have to add a new disk on virtual hardware level. I. e. extending disk space never means enlarging existing disks.

- [Extending VMWare Disk](#)
- [Extending Hyper-V Disk](#)
- [Enlarging the Partition in the Appliance](#)

Extending VMWare Disk

Extending the virtual disk is done using the VMWare host application. Here are examples for VMWare Workstation and vSphere:






Please restart the virtual appliance after adding the new disk.



Extending Hyper-V Disk

To extend the virtual disk, open the virtual machine properties and follow the steps below:


1. Navigate to *IDE Controller 0*, select *Hard drive* and click **Add**



2. Select **New** and finish the wizard:



3. After finishing the wizard click **Ok** to exit the Settings:




Please restart the virtual appliance after adding the new disk.


Enlarging the Partition in the Appliance

1. The easiest way to enlarge a partition in the appliance is to use the installed partition manager **GParted**. Please launch it using the Applications menu (you can also start GParted from the Terminal with "sudo gparted"):

2. Select the new physical disk:




3. Select the unallocated space, open the *Device* menu and on click on **Create Partition Table**:




4. Click on *Apply* in the warning:



5. Select the new *unallocated* space, right-click and select *New*.



6. From the *Create as* drop down menu, select **Primary Partition** and chose **lvm2 pv** as *File system* (if needed, a *Label* can be defined):




7. Save your changes by clicking the **apply button** - also on the popup message




8. Start the **Logical Volumes Manager** from the Applications menu


9. Open the *Logical View* on the left hand side, select *Physical View* and click **Extend VolumeGroup**:




10. Select your new volume and click **OK**:




11. After this, select the logical volume **opt_panagenda_appdata**:



12. Resize the logical volume as needed (initial dimensioning: 5MB x database instances - for more details, please refer to the [Setup Guide](#)):



13. Select the logical volume `opt_panagenda_pgdata` (for more details on initial dimensioning, please refer to the [Setup Guide](#)):



14. Resize the logical volume as needed (see step 12)

Tip

You can repeat this enlargement whenever you need more space.